

INSTALLATION

Table of contents

1. Introduction	2
2. Installation	3
2.1. Hardware requirement.....	3
2.2. Installation of the system.....	3
2.3. Installation of ALCASAR.....	8
2.4. Connection to the ALCASAR Control Center.....	11
3. Stop, uninstall or update ALCASAR	12
4. Your ALCASAR settings sheet	12

Project : ALCASAR	Author : Rexy with help from “Alcasar team”. Thanks to translators.
Object : Installation	Version : 3.5.3
Keywords : Network Access Control (NAC), accountability, traceability, authentication, captive portal, parental control.	Date : 2021, April


1. Introduction

This document describes the installation procedure of the ALCASAR portal. It is supplemented with three other documents : the presentation document, the operating instructions document and the technical document.

If you already have a working version of ALCASAR and you want to upgrade it, please refer to the operating instructions document (chapter « update »).

ALCASAR can be installed on a standard computer with two Ethernet network cards. The first one (eth0) is connected to the Internet Service Provider equipment. The second one (eth1) is connected to the switch used to service the network consultation computers.

By default, the IP address of this second network card is : 192.168.182.1/24. This allows you to have a class C network (254 equipment). This network addressing plan can be modified during the installation stage. For all equipment of consultation network, ALCASAR is the DHCP server, the DNS server, the network time-server and the default router (gateway). **Thus, on this network, there must be no other DHCP server and gateway** (check your Wi-Fi access points).



Examples of IP addressing plans

Parameters	@IP of the network	Number of equipment	Network mask	@IP of ALCASAR (this address is the IP address of the DNS server and of the default gateway)	DNS suffix
Classe					
Default IP address plan (C class)	192.168.182.0/24	253	255.255.255.0	192.168.182.1/24	localdomain
B class IP plan	172.16.x.0/16 $1 \leq x \leq 255$	65533	255.255.0.0	172.16.x.1/16	localdomain

Even if it is possible to define a class A network, you shouldn't do it because the embedded DHCP server will have to manage over than 16 million IP addresses. The management of such volume of addresses would spend too much memory.

2. Installation

The installation of ALCASAR consists of two steps. The first one is the installation of a minimalist Linux operating system based on Linux-Mageia. The second step is to run a script which installs and configures all the components of ALCASAR.

2.1. Hardware requirement

ALCASAR only requires one standard computer (PC) or a virtual machine (VM) with two network cards and a hard drive with a capacity of at least 100 Go in order to be able to store logs related to connections tracing. Only 64b architectures are supported. ALCASAR includes several optional filtering systems (network protocols, URL, IP addresses, domain names and antimalware). If you decide to enable these filtering systems, it is recommended to install at **least 8 GB** of RAM in order to ensure an acceptable processing speed (ALCASAR loves the RAM ;-)).

 **On a VM**, the following information must be kept in mind :

- the size of the dynamic hard drive must not be smaller than 30G;
- The graphic card should be as simple as possible (“vga” generally).
- On KVM/QEMU hypervisors like “Promox”, the network cards (NIC) mustn’t be “virtio” type (choose “e1000” or “Intel-pro1000” for example); You can also let the VM manage the real NIC of the PC. To do that, after removing the virtual NIC, choose the following options : « Add hardware » + « Host PCI peripheral » + choose the PCI card corresponding to your physical network card.
- A complementary document is published on ALCASAR WEB site. It explains the installation of ALCASAR on « Virtualbox » or « Proxmox ».








2.2. Installation of the system








The installation procedure of the operating system is the following (estimated time : 6') :








- Retrieve the ISO file of **version 7.1** of Linux-Mageia (file : « mageia-7.1-x86_64-DVD.iso ») on [Mageia website](#) as well as on several [mirror sites of Mageia](#). Another solution is to retrieve the ISO file we specially create for ALCASAR. This file is downloadable on the ALCASAR web site or in the folder “iso” of the site <ftp.alcasar.net>. This file isn’t always available when a new version of ALCASAR is ready.
- On a PC:
 - Burn this ISO image file on a removable support (CD, DVD, USB flash drive)¹;
 - Configure the BIOS settings to remove the “Secure Boot” option, to set the date and time and to enable booting from the CD or USB flash drive. At the end of the installation, configure, once again, the BIOS settings to only boot from the hard drive;
 - Insert your removable support. Reboot the computer and follow the instructions below :
- On a VM:
 - Copy the ISO file in the dedicated zone of the hypervisor. Link this ISO image to your VM. Boot your VM.







¹ Two solutions are used to create a bootable USB flash drive :

- in graphical mode you can use “rufus” or “win32 disk image” (Windows) or “isodumper” (Linux)
- in console mode on Linux, plug the USB flash drive and get the name of the device with the “`fdisk -l`” command (a USB flash drive is usually “/dev/sdb” or “/dev/sdc”). Run the command : “`dd if=<name_of_ISO_image> of=<name_of_usb_drive> bs=1M`”.

Screen display	Comments	Actions to achieve
 <p>Mageia 7.1 (64-bit)</p> <p>Install Mageia Rescue System Memory Test</p> <p>F2: Language []</p>  <p>Mageia 7.1 (64-bit EFI)</p> <p>Install Mageia Rescue System</p> <p>F2: Language []</p>	<p>After starting the computer, one of these screens is displayed.</p> <p>* If the graphical mode doesn't work, you have to configure the BIOS settings to allocate more than 2 MB of shared memory for the graphics card.</p>	<p>Reading the first line of this screen, you know if your PC (or VM) use a legacy BIOS or an EFI BIOS. Remember the type of your BIOS.</p> <p>Select "Install Mageia".</p>
 <p>PLEASE CHOOSE A LANGUAGE TO USE</p> <ul style="list-style-type: none"> Asia Africa Europe America <ul style="list-style-type: none"> Avarle'ë English (British) English (American) English (Canada) Español Esperanto Français Kalaallisut Português do Brasil Runa Simi <p><input type="checkbox"/> Multiple languages</p> <p><input type="checkbox"/> Help Next</p>		<p>Select your language and click "Next".</p>
 <p>LICENSE AGREEMENT</p> <p>Introduction The operating system and the different components available in the Mageia distribution shall be called the "software products" hereafter. The Software Products include, but are not restricted to, the set of programs, methods, rules and documentation related to the operating system and the different components of the Mageia distribution, and any applications distributed with these products provided by Mageia's licensors or suppliers.</p> <p>1. License Agreement Please read this document carefully. This document is a license agreement between you and Mageia which applies to the Software Products. By installing, duplicating or using any of the Software Products in any manner, you explicitly accept and fully agree to conform to the terms and conditions of this License. If you disagree with any portion of the License, you are not allowed to install, duplicate or use the Software Products. Any attempt to install, duplicate or use the Software Products in a manner which does not comply with the terms and</p> <p>Do you accept this license ?</p> <p><input checked="" type="radio"/> Accept <input type="radio"/> Refuse</p> <p><input type="checkbox"/> Release Notes</p> <p><input type="checkbox"/> Help Quit Next</p>		<p>Accept the license agreement then click "Next".</p> <p>Info: this license agreement explains that the installed software is free (GPL).</p>
 <p>KEYBOARD</p> <p>Please choose your keyboard layout</p> <p><input type="radio"/> Dvorak (US)</p> <p><input type="radio"/> ISO9995-3 (US keyboard with 3 levels per key)</p> <p><input checked="" type="radio"/> US keyboard</p> <p><input type="radio"/> US keyboard (international)</p> <p><input type="checkbox"/> More</p>		<p>Choose your keyboard layout and click "Next".</p>
 <p>PARTITIONING</p> <p>Here is the content of your disk drive ATA VBOX HARDISK (8GB)</p> <p>ext4 XFS Swap Windows Other Empty</p> <p>The DrakX Partitioning wizard found the following solutions:</p> <p><input type="radio"/> Use existing partitions</p> <p><input type="radio"/> Erase and use entire disk</p> <p><input checked="" type="radio"/> Custom disk partitioning</p>	<p>The hard disk partitioning will be adapted to the needs of ALCASAR (see next step).</p>	<p>Select "Custom disk partitioning" then click "Next".</p>
 <p>PARTITIONING</p> <p>Click on a partition, choose a filesystem type then choose an action</p> <p>sda</p> <p>ext4 XFS Swap Windows Other Empty</p> <p>Details Empty Size: 7.9GB (99%) Cylinder 0 to 1043</p> <p>Clear all Auto allocate</p>	<p>After removing all the partitions, create the following 5 or 6 partitions :</p> <p>! Create the 1st "/boot/efi" partition only if you have an EFI BIOS.</p> <ul style="list-style-type: none"> • /boot/EFI/ : 300 MB (type "efi") • / : 5 GB (type "ext4") • swap : 5 GB (type "Linux swap") • /tmp : 5 GB (type "ext4") • /home : 5 GB (type "ext4") • /var : (type "ext4") the rest of the hard drive (! the size of 'var' must be bigger than 10GB even on a virtual machine). 	<p>Click on "Clear all".</p> <p>Then click on the area of the disk (sda) to create each new partition.</p>

Screen display	Comments	Actions to achieve
	<p>At the end of this operation, and depending on the size of your hard drive, the partitioning should look like this :</p> 	<ul style="list-style-type: none"> - Create the root partition (/). Choose its size (5 Go) and its filesystem (ext4). Repeat this step for all the partitions. - Once the partitioning completed, click on “Done”.
	<p>For ALCASAR, it does not need any other media.</p>	<p>Select “None” then click “Next”.</p>
	<p>This screen isn't displayed if you use the ISO file we specially create for ALCASAR.</p>	<p>Leave the “Nonfree Release” media enabled then click “Next”.</p>
	<p>This screen isn't displayed if you use the ISO file we specially create for ALCASAR.</p> <p>ALCASAR doesn't need a graphical environment (it is controlled from a WEB browser).</p>	<p>Select “Custom” then click “Next.”</p>
	<p>This screen isn't displayed if you use the ISO file we specially create for ALCASAR.</p> <p>Package group selection : ALCASAR only requires a very minimal install.</p>	<p>Select “Unselect All” then click “Next”.</p> <p>Info: On Linux, a package is an archive file containing all the components of a specific software (binary files, help files, configuration files, etc.).</p>
	<p>This screen isn't displayed if you use the ISO file we specially create for ALCASAR.</p>	<p>Select only “Install recommended packages” and the basic documentation, then click “Next”.</p> <p>The copy of the packages is launched. Estimated time : 2'</p>

Screen display	Comments	Actions to achieve
		<p>Assign a password to the "root" account, then, create the "sysadmin" account and assign it a password. Then, click "Next".</p>
	<p>Configuration of your time zone and your country</p>	<p>In the group "System", click on "Configure" in "time zone" section then in "Country" section. Select your time zone and your country.</p>
		<p>Click on "Configure" in "Network-ethernet" in the "Network & Internet" section.</p>
		<p>Select the type of Internet connection. In the case of the use of an ISP broadband modem, choose "Wired (Ethernet)". Then, click "Next".</p> <p>Info : no test has yet been made on other types of Internet access.</p>
	<p>At that time, only the interface connected to the broadband modem of the ISP has to be configured. The second interface, connected to the consultation network, will be configured later, during the installation of ALCASAR.</p>	<p>Select the interface to configure, then click "Next".</p> <p>Tips : Choose the interface with the smallest index. Write the name of this interface on a paper.</p> <p>Info : the names of interfaces are linked with the physical architecture of your PC. They could differ from the printscreen.</p>
		<p>Select "Manual configuration", then click "Next".</p> <p>Info : While it is possible to let this interface in "bootp/dhcp" mode, we recommended configuring it manually (static mode).</p>
	<p>Example :</p> <ul style="list-style-type: none"> • IP address : this address must be in the same sub-net as the address of the broadband modem. • Netmask : 255.255.255.0 • Gateway : This is the address of the broadband modem. • DNS 1 and DNS 2 :* • Host name : Leave the default value (or blank) 	<p>Enter the parameters of this interface</p> <p>* Enter the IP addresses of the DNS servers provided by your ISP. You can also use other DNS servers. Examples:</p> <ul style="list-style-type: none"> • Free project "OpenNic" (see the web site to know the closest servers for you) • Association (FR) FDN (DNS1=80.67.169.12, DNS2=80.67.169.40) • Association (US) Quad9 (DNS1=9.9.9.9) • Association (US) Cloudflare (DNS1=1.1.1.1, dns2=1.0.0.1) • project "OpenDNS" (DNS1=208.67.222.222, DNS2=208.67.220.220) • Google (DNS1=8.8.8.8, DNS2=8.8.4.4).

Screen display	Comments	Actions to achieve
		<p>Select only "Start the connection at boot", the click "Next".</p>
	<p>It is not necessary to start the connection now.</p>	<p>Select "No", then click "Next".</p>
		<p>Click on "Finish"</p>
		<p>Click "Next"</p>
	<p>If you use the ISO file we specially create for ALCASAR, the installation will continue (white screen) and the system will reboot automatically.</p> <p>Security updates will be managed during the installation of ALCASAR.</p>	<p>Select "No" and click on "Next".</p>
	<p>If you use the ISO file we specially create for ALCASAR, the installation will continue (white screen) and the system will reboot automatically.</p> <p>The installation is finished.</p>	<p>Click on "Reboot" Remove the CDROM or the USB flash drive. Reconfigure the BIOS to boot only from the hard drive.</p>

2.3. Installation of ALCASAR

Configuration of the network cards

Screen display	Comments	Actions to achieve
<pre>Mageia release 6 (Official) for x86_64 Kernel 4.9.35-desktop-1.mga6 on a x86_64 / tty1 localhost login: root Password:</pre>	<p>Disconnect the cables of the two network cards.</p> <p>Log in as root</p>	
<pre>1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN mode DEFAULT g 1000 link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00 2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP mode default qlen 1000 link/ether 08:00:27:aa:bc:aa brd ff:ff:ff:ff:ff:ff 3: enp0s8: <NO-CARRIER,BROADCAST,MULTICAST,UP> mtu 1500 qdisc fq_codel state DOWN default qlen 1000 link/ether 08:00:27:bc:56:d3 brd ff:ff:ff:ff:ff:ff</pre>	<p>Display continuously the state of the network cards.</p> <p>When you plug a cable in a network card, the “state” change from “DOWN” to “UP”.</p>	<p>watch ip link</p> <p><i>You have to connect the cable linked to the ISP broadband modem (Internet access) in the network interface you have previously configured (normally, the interface with the smallest index).</i></p>
<pre>1: lo: <LOOPBACK,UP,LOWER_UP> mtu 65536 qdisc noqueue state UNKNOWN mode DEFAULT 1000 link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00 2: enp0s3: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP m default qlen 1000 link/ether 08:00:27:aa:bc:aa brd ff:ff:ff:ff:ff:ff 3: enp0s8: <BROADCAST,MULTICAST,UP,LOWER_UP> mtu 1500 qdisc fq_codel state UP m default qlen 1000 link/ether 08:00:27:bc:56:d3 brd ff:ff:ff:ff:ff:ff</pre>	<p>The two network interface must be “up” to continue the install process.</p>	<p>Connect the second network interface to the switch of your internal LAN. Verify that the two interfaces are “up”. Then stop the command with the <Ctrl> + c keys</p>
<pre>[root@localhost ~]# ping -c3 www.google.fr PING www.google.fr (216.58.211.99) 56(84) bytes of data: 64 bytes from par03s15-in-f99.1e100.net (216.58.211.99): icmp_s 64 bytes from par03s15-in-f99.1e100.net (216.58.211.99): icmp_s 64 bytes from par03s15-in-f99.1e100.net (216.58.211.99): icmp_s --- www.google.fr ping statistics --- 3 packets transmitted, 3 received, 0% packet loss, time 2003ms rtt min/avg/max/mdev = 28.971/29.768/30.546/0.658 ms</pre>	<p>Test your Internet connectivity</p>	<p>ping -c3 google.com (or another Internet site)</p>



Download the ALCASAR installation file

This file is an archive file named : `alcasar-x.y.tar.gz` ('x.y' means the version number you want).



If you've installed Linux-Mageia with the ISO we specially create for ALCASAR (Mageiar), this file has already been uncompressed in the `"/root/alcasar-x-y"` directory. Go to the installation step.

In the other cases, you can download this file with two different ways (via HTTP or via a USB flash drive):



- Via HTTP : on the ALCASAR PC, download the last version stored on the server "ftp.alcasar.net"

Screen display	Comments	Actions to achieve
		With a desktop PC, connect a Web browser to the server " ftp.alcasar.net " and look at the available ALCASAR installation files (in the folder "stable").
	On the ALCASAR computer, download the installation file you want.	<code>curl -O http://ftp.alcasar.net/stable/alcasar-3.5.tar.gz</code>

- via a USB flash drive : From a Desktop PC, download the latest version of the ALCASAR (website or ftp.alcasar.net). Copy this file on an USB flash drive. Then, use the following procedure to copy it on the ALCASAR computer :


Screen display	Comments	Actions to achieve
	Insert the USB flash drive. Display information on mass media storage to get the name of your USB flash drive. In this example, <code>"/dev/sdb1"</code> is a 1 GB USB flash drive.	<code>fdisk -l</code> Info : You also can display the system log to get this name (<code>journalctl -f</code>).
	<ul style="list-style-type: none"> • Create a directory and mount the USB flash drive on it. • Copy the archive of ALCASAR to the directory <code>"/root"</code>. • Unmount the USB flash drive. • Unplug it. 	<code>mkdir -p /media/usb</code> <code>mount /dev/sdb1 /media/usb/</code> <code>cp /media/usb/alcasar-* /root/</code> <code>umount /media/usb</code> Info : Replace "sdb1" with the device name retrieved in the previous step.

Decompression of the ALCASAR installation file

	<ul style="list-style-type: none"> • Compute the SHA256 digital footprint of this installation file and compare it with that of the website. 	<code>sha256sum alcasar-x.y.tar.gz</code> Info : If the digital footprint doesn't match, download the archive again. If the problem occurs one more time, ask the developer team via the forum.
	<ul style="list-style-type: none"> • Decompress this archive. 	<code>tar -xvf alcasar-x.y.tar.gz</code>

2.4. Connection to the ALCASAR Control Center

On the consultation network, connect a PC and run a WEB browser with the URL “<http://alcasar.localdomain>” in order to display the following page :



Click on the small crated wheel at the bottom right in order to connect to the ALCASAR Control Center (ACC). You must authenticate you with the first account created during the installation process (§2.3 – P10 of this document). Now, read the exploitation documentation (“[alcasar-exploitation-en.pdf](#)”) to create your first “user” accounts.

You can also display this page by clicking the link in the explanation text of the user’s interception page:



3. Stop, uninstall or update ALCASAR

Stop: You can stop the ALCASAR computer with a brief push on the power button of the PC, or with the command « `poweroff` » or via the WEB ALCASAR Control Center (ACC – menu “system” + “services”).

Uninstall: You can uninstall ALCASAR with the command « `sh alcasar.sh --uninstall` ». This command uninstalls only ALCASAR. The operating system (Linux Mageia) is still present.

Update: If you launch again the installation script on an already installed ALCASAR, the script will ask you if you want to update or to install again (cf. §8 of the exploitation documentation).

4. Your ALCASAR settings sheet

The file « `/root/ALCASAR-passwords.txt` » contains passwords used internally by the different modules of ALCASAR. It contains, more particularly, the password protecting the bootloader (« GRUB2 »). It can be consulted via the command « `cat /root/ALCASAR-passwords.txt` ». Be careful : when you enter the GRUB password, your keyboard is mapped like a “qwerty” keyboard.

Organization name :	
Users authentication page	This page is displayed when a browser tries to access a HTTP website.
The welcome page of ALCASAR allows: <ul style="list-style-type: none"> • to access the ALCASAR Control Center. • log the users out • change the users password • install the certificate of the Certification Authority (C.A.) in the browsers. 	http://alcasar.localdomain Info : The possibilities of the ALCASAR Control Center (ACC) are described in the "ALCASAR-exploitation-en.pdf" document.
Linux accounts	root password : sysadmin password :
First ALCASAR WEB administrative account	Login: password :
Network parameters <ul style="list-style-type: none"> • IP address of the ISP's equipment (router) : • IP address of DNS servers : • IP address of ALCASAR (WAN/Internet side) : • IP address of ALCASAR (LAN side) : 	<ul style="list-style-type: none"> • _____ • DNS1 : _____ • DNS2 : _____ • _____/_____ • _____/_____